

ADEI addressing

There is two ways of addressing ADEI channels.

- Using just unique *uid* identifiers
- Using full specification

The *uid* identifiers should start from the letter of English alphabete and may contain alphanumeric characters and underscores.

The full specification is including the data source id, database id, group id, and channel specification. All parts are concatenated using double underscore (__). The channel specification can be a channel number or *uid*.

Examples:

- TI5130
- db_server__db_name__db_group__0
- db_server__db_name__db_group__TI5130
- db_server__db_name__control_group__TC5130

Addressing of multiple channels

Multiple channels are specified using comma-separated lists.